#### NAME

crosstab - contingency table (or crosstabulation) analysis

## SYNOPSIS

crosstab [<] contingency\_table > stderr

# DESCRIPTION

*crosstab* calculates measures of 1) significance of association and 2) strength of association for a contingency table. It reads either an ASCII file or an unsigned long (PFUINT) HIPS file containing the *contingency\_table*. If read from *stdin* only ASCII files are allowed. The first two numbers in the ASCII file are number of rows *nr* and number of columns *nc*. The ASCII file is read row-wise.

The significance of association is measured by a chi-square test for no association between rows and columns. The corresponding significance level gives the probability of finding a larger chi-square (small values indicating a significant association). Also Cramer's V, the contingency coefficient C, and the phi coefficient are calculated. If the table is quadratic the diagonal sum and kappa (with *t*-test of significance) are calculated.

The strength of association (if significant) is measured by entropy measures, specifically the uncertainty of the rows given the columns,  $U(\mathbf{r}|\mathbf{c})$ , vice versa,  $U(\mathbf{c}|\mathbf{r})$ , and a symmetrical uncertainty measure,  $U(\mathbf{r},\mathbf{c})$ .

## REFERENCES

J.B. Campbell (1996). Introduction to Remote Sensing. Second Edition. Taylor and Francis, London.

K. Conradsen (1984). En Introduktion til Statistik 1B. 4. udgave. (In Danish.)

J.W. Dixon et al. (1985). BMDP Manual.

W.H. Press, S.A. Teukolsky, W.T. Vetterling and B.P. Flannery (1997). *Numerical Recipes in C: The Art of Scientific Computing*. Second Edition. Cambridge University Press.

## AUTHOR

Allan Aasbjerg Nielsen, M.Sc., Ph.D. IMM, Department of Mathematical Modelling Technical University of Denmark, Building 321 E-mail aa@imm.dtu.dk, Internet http://www.imm.dtu.dk/~aa